

HOW TO: UPPER WEST BRONDE

◆ **STARTING LEVEL:**
Natural level 6
50% gray
Previous highlights

◆ **ARTIST:**
Sean Godard

FORMULA

ZONE 1 FORMULA


- 1 oz. Color Gels Oils 7N
- 1 oz. Color Gels Oils 9N
- 2 oz. 20 vol. Pro-oxide Cream Developer

ZONE 3 FORMULA

- 2 oz. Shades EQ Bonder Inside 10G
- 2 oz. Shades EQ Processing Solution

ZONE 2 FORMULA

- 2 oz. Color Gels Oils 10IG
- 2 oz. 20 vol. Pro-oxide Cream Developer






SECTIONING

+ STEP 1

Follow the natural part and separate the front from the back with a vertical parting from the high point of the head to the top of the ear.

Repeat on the opposite side.




+ STEP 2

Divide the back equally with a vertical parting from the high point of the head parting to the center of the nape.

Secure 4 quadrants.

+ STEP 3

Apply Zone 3 Formula starting from the front right quadrant to Zone 3 working from the bottom section up and blurring the Formula into Zone 2. Repeat on opposite side and then back two quadrants.




+ STEP 4

Rinse and shampoo with Acidic Color Gloss, then treat with Acidic Bonding Concentrate 5 Min Leave-In Treatment. Dry and style hair.

APPLICATION

+ STEP 1

Begin by applying Zone 1 Formula to the first 1"-1.5" of the front right quadrant. Take diagonal back sub sections as you work. Work from top to bottom and repeat on opposite front side. After that side is complete, repeat in back.



+ STEP 2

Apply Zone 2 Formula starting from the front right quadrant to Zone 2 working from the bottom section up and blurring the Formula into Zone 1. Repeat on opposite side and then back two quadrants.

